

How to Set Up Email on iPhone Using IMAP

LOG IN TO THE CPANEL INTERFACE AND CREATE THE MAILBOX YOU WANT TO SET UP

1. Log in to the cPanel interface.
2. Create a mailbox! ([How to create e-mailbox in cPanel?](#))
3. After creating the mailbox, in the cPanel interface, under E-mail Accounts in the Mailbox, scroll down to E-mail Accounts and click Set Up Mail Client. CPanel will display the information required for setup.

If you want to use the **mail.yourdomain.tld** server in the description, replace it with your own domain name.

If you want to use the **hostingID.loginssl.com** server, enter your cPanel username instead of hostingID.

THE SETUP PROCEDURE:

1. On your device, go to the **Settings** menu and select **Mail**.
Settings / Mail
Settings / Mail
2. On the page that appears, select **Add Account**
Accounts and Passwords / Adding account
Accounts and Passwords / Adding account
3. On the Add Account screen, select **Other**
Welcome the Mail / Other
Welcome the Mail / Other
4. On the next screen, select **Add Mail Account**
5. On the New Account screen, fill in the mailbox information form with the following information based on the information in the image, then tap
New account
New account

the **Next** option

For IMAP mail, both Incoming and Outgoing mail servers are as follows:

hostingID.loginssl.com

Before the address ending in .loginssl.com in the image and above, you must enter your hosting ID, which is the same as the username for the cPanel interface. To view your

cPanes login at <https://admin.dotroll.com>, follow these steps:

1. After logging in, click **Services / My Services** in the top menu bar.
2. On the page that appears, click the Active button at the end of the hosting service line for that domain name.
3. In the middle of the page, under the Hosting Information tab, you will find the cPanel user name.
6. The device automatically tries to connect to the mail server based on the entered information.
Searching Account
Searching Account
7. After a successful connection, the following screen will appear
Accounts
Accounts
8. After that, if you tap > next to the set account, you can view the account details or update the account settings here.
Accounts Information
Accounts Information
9. Mail sending information can be set by touching the > sign at the end of the SMTP line
SMTP
SMTP
10. Here, tap > next to the configured server, and then make sure the outgoing mail server is set up as shown.
Outgoing Mail Server
Outgoing Mail Server
11. You can specify other advanced settings for your account by selecting Advanced Settings at the bottom of the screen
Advanced
Advanced

Revision #4

Created 2023-10-25 12:41:20 CEST by DotRoll Knowledge Base

Updated 2026-05-18 11:23:59 CEST by DotRoll Knowledge Base